

Package ‘AID’

February 18, 2025

Type Package

Title Box-Cox Power Transformation

Version 3.1

Date 2025-02-18

Depends R (>= 3.2.0)

Imports MASS, tseries, nortest, ggplot2, graphics, psych, stats, meta, stringr

Suggests onewaytests

Author Osman Dag [aut, cre],

Muhammed Ali Yilmaz [aut],

Ozgur Asar [ctb],

Ozlem Ilk [ctb]

Maintainer Osman Dag <osman.dag@outlook.com>

Description Performs Box-Cox power transformation for different purposes, graphical approaches, assesses the success of the transformation via tests and plots, computes mean and confidence interval for back transformed data.

License GPL (>= 2)

NeedsCompilation no

Repository CRAN

Date/Publication 2025-02-18 22:40:06 UTC

Contents

AID-package	2
AADT	2
boxcoxfr	3
boxcoxlm	6
boxcoxmeta	8
boxcoxnc	9
confInt.boxcoxfr	11
confInt.boxcoxmeta	13

confInt.boxcoxnc	14
grades	15
textile	15

Index**17**

AID-package	<i>Box-Cox Power Transformation</i>
-------------	-------------------------------------

Description

Performs Box-Cox power transformation for different purposes, graphical approaches, assesses the success of the transformation via tests and plots, computes mean and confidence interval for back transformed data.

Details

Package: AID
 Type: Package
 License: GPL (>=2)

AADT	<i>Average Annual Daily Traffic Data</i>
------	--

Description

Average annual daily traffic data collected from the Minnesota Department of Transportation data base.

Usage

```
data(AADT)
```

Format

A data frame with 121 observations on the following 8 variables.

aadt average annual daily traffic for a section of road
 ctypop population of county
 lanes number of lanes in the section of road
 width width of the section of road (in feet)
 control a factor with levels: access control; no access control
 class a factor with levels: rural interstate; rural noninterstate; urban interstate; urban noninterstate
 truck availability situation of road section to trucks
 locale a factor with levels: rural; urban, population <= 50,000; urban, population > 50,000

References

- Cheng, C. (1992). Optimal Sampling for Traffic Volume Estimation, Unpublished Ph.D. dissertation, University of Minnesota, Carlson School of Management.
- Neter, J., Kutner, M.H., Nachtsheim, C.J., Wasserman, W. (1996). *Applied Linear Statistical Models* (4th ed.), Irwin, page 483.

Examples

```
library(AID)

data(AADT)
attach(AADT)
hist(aadt)
out <- boxcoxfr(aadt, class)
confInt(out)
```

boxcoxfr

Box-Cox Transformation for One-Way ANOVA

Description

`boxcoxfr` performs Box-Cox transformation for one-way ANOVA. It is useful to use if the normality or/and the homogeneity of variance is/are not satisfied while comparing two or more groups.

Usage

```
boxcoxfr(y, x, option = "both", lambda = seq(-3, 3, 0.01), lambda2 = NULL,
tau = 0.05, alpha = 0.05, verbose = TRUE)
```

Arguments

<code>y</code>	a numeric vector of data values.
<code>x</code>	a vector or factor object which gives the group for the corresponding elements of <code>y</code> .
<code>option</code>	a character string to select the desired option for the objective of transformation. "nor" and "var" are the options which search for a transformation to satisfy the normality of groups and the homogeneity of variances, respectively. "both" is the option which searches for a transformation to satisfy both the normality of groups and the homogeneity of variances. Default is set to "both".
<code>lambda</code>	a vector which includes the sequence of feasible lambda values. Default is set to (-3, 3) with increment 0.01.
<code>lambda2</code>	a numeric for an additional shifting parameter. Default is set to <code>lambda2 = 0</code> .
<code>tau</code>	the feasible region parameter for the construction of feasible region. Default is set to 0.05. If <code>tau = 0</code> , it returns the MLE of transformation parameter.
<code>alpha</code>	the level of significance to check the normality and variance homogeneity after transformation. Default is set to <code>alpha = 0.05</code> .
<code>verbose</code>	a logical for printing output to R console.

Details

Denote y the variable at the original scale and y' the transformed variable. The Box-Cox power transformation is defined by:

$$y' = \begin{cases} \frac{y^\lambda - 1}{\lambda}, & \text{if } \lambda \neq 0 \\ \log(y), & \text{if } \lambda = 0 \end{cases}$$

If the data include any nonpositive observations, a shifting parameter λ_2 can be included in the transformation given by:

$$y' = \begin{cases} \frac{(y + \lambda_2)^\lambda - 1}{\lambda}, & \text{if } \lambda \neq 0 \\ \log(y + \lambda_2), & \text{if } \lambda = 0 \end{cases}$$

Maximum likelihood estimation in feasible region (MLEFR) is used while estimating transformation parameter. MLEFR maximizes the likelihood function in feasible region constructed by Shapiro-Wilk test and Bartlett's test. After transformation, normality of the data in each group and homogeneity of variance are assessed by Shapiro-Wilk test and Bartlett's test, respectively.

Value

A list with class "boxcoxfr" containing the following elements:

method	method applied in the algorithm
lambda.hat	the estimated lambda
lambda2	additional shifting parameter
shapiro	a data frame which gives the test results for the normality of groups via Shapiro-Wilk test
bartlett	a matrix which returns the test result for the homogeneity of variance via Bartlett's test
alpha	the level of significance to assess the assumptions.
tf.data	transformed data set
x	a factor object which gives the group for the corresponding elements of y
y.name	variable name of y
x.name	variable name of x

Author(s)

Osman Dag, Ozlem Ilk

References

Dag, O., Ilk, O. (2017). An Algorithm for Estimating Box-Cox Transformation Parameter in ANOVA. *Communications in Statistics - Simulation and Computation*, **46:8**, 6424–6435.

Examples

```
#####
# Communication between AID and onewaytests packages

library(AID)
library(oneyawaytests)

# Average Annual Daily Traffic Data (AID)
data(AADT)

# to obtain descriptive statistics by groups (onewaytests)
describe(aadt ~ class, data = AADT)

# to check normality of data in each group (onewaytests)
nor.test(aadt ~ class, data = AADT)

# to check variance homogeneity (onewaytests)
homog.test(aadt ~ class, data = AADT, method = "Bartlett")

# to apply Box-Cox transformation (AID)
out <- boxcoxfr(AADT$aadt, AADT$class)

# to obtain transformed data
AADT$tf.aadt <- out$tf.data

# to conduct one-way ANOVA with transformed data (onewaytests)
result<-aov.test(tf.aadt ~ class, data = AADT)

# to make pairwise comparison (onewaytests)
paircomp(result)

# to convert the statistics into the original scale (AID)
confInt(out, level = 0.95)

#####
library(AID)

data <- rnorm(120, 10, 1)
factor <- rep(c("X", "Y", "Z"), each = 40)
out <- boxcoxfr(data, factor, lambda = seq(-5, 5, 0.01), tau = 0.01, alpha = 0.01)
confInt(out, level = 0.95)

#####
```

boxcoxlm*Box-Cox Transformation for Linear Models***Description**

`boxcoxlm` performs Box-Cox transformation for linear models and provides graphical analysis of residuals after transformation.

Usage

```
boxcoxlm(x, y, method = "lse", lambda = seq(-3,3,0.01), lambda2 = NULL, plot = TRUE,
alpha = 0.05, verbose = TRUE)
```

Arguments

<code>x</code>	a nxp matrix, n is the number of observations and p is the number of variables.
<code>y</code>	a vector of response variable.
<code>method</code>	a character string to select the desired method to be used to estimate Box-Cox transformation parameter. To use Shapiro-Wilk test method should be set to "sw". For method = "ad", <code>boxcoxnc</code> function uses Anderson-Darling test to estimate Box-Cox transformation parameter. Similarly, method should be set to "cvm", "pt", "sf", "lt", "jb", "mle", "lse" to use Cramer-von Mises, Pearson Chi-square, Shapiro-Francia, Lilliefors and Jarque-Bera tests, maximum likelihood estimation and least square estimation, respectively. Default is set to method = "lse".
<code>lambda</code>	a vector which includes the sequence of candidate lambda values. Default is set to (-3,3) with increment 0.01.
<code>lambda2</code>	a numeric for an additional shifting parameter. Default is set to <code>lambda2 = 0</code> .
<code>plot</code>	a logical to plot histogram with its density line and qqplot of residuals before and after transformation. Defaults <code>plot = TRUE</code> .
<code>alpha</code>	the level of significance to assess the normality of residuals after transformation. Default is set to <code>alpha = 0.05</code> .
<code>verbose</code>	a logical for printing output to R console.

Details

Denote y the variable at the original scale and y' the transformed variable. The Box-Cox power transformation is defined by:

$$y' = \begin{cases} \frac{y^\lambda - 1}{\lambda} = \beta_0 + \beta_1 x_1 + \dots + \epsilon, & \text{if } \lambda \neq 0 \\ \log(y) = \beta_0 + \beta_1 x_1 + \dots + \epsilon, & \text{if } \lambda = 0 \end{cases}$$

If the data include any nonpositive observations, a shifting parameter λ_2 can be included in the transformation given by:

$$y' = \begin{cases} \frac{(y+\lambda_2)^\lambda - 1}{\lambda} = \beta_0 + \beta_1 x_1 + \dots + \epsilon, & \text{if } \lambda \neq 0 \\ \log(y + \lambda_2) = \beta_0 + \beta_1 x_1 + \dots + \epsilon, & \text{if } \lambda = 0 \end{cases}$$

Maximum likelihood estimation and least square estimation are equivalent while estimating Box-Cox power transformation parameter (Kutner et al., 2005). Therefore, these two methods return the same result.

Value

A list with class "boxcoxlm" containing the following elements:

method	method preferred to estimate Box-Cox transformation parameter
lambda.hat	estimate of Box-Cox Power transformation parameter based on corresponding method
lambda2	additional shifting parameter
statistic	statistic of normality test for residuals after transformation based on specified normality test in method. For mle and lse, statistic is obtained by Shapiro-Wilk test for residuals after transformation
p.value	p.value of normality test for residuals after transformation based on specified normality test in method. For mle and lse, p.value is obtained by Shapiro-Wilk test for residuals after transformation
alpha	the level of significance to assess normality of residuals
tf.y	transformed response variable
tf.residuals	residuals after transformation
y.name	response name
x.name	x matrix name

Author(s)

Osman Dag, Ozlem Ilk

References

- Asar, O., Ilk, O., Dag, O. (2017). Estimating Box-Cox Power Transformation Parameter via Goodness of Fit Tests. *Communications in Statistics - Simulation and Computation*, **46:1**, 91–105.
- Kutner, M. H., Nachtsheim, C., Neter, J., Li, W. (2005). *Applied Linear Statistical Models*. (5th ed.). New York: McGraw-Hill Irwin.

Examples

```
library(AID)

trees=as.matrix(trees)
boxcoxlm(x = trees[,1:2], y = trees[,3])
```

boxcoxmeta

Ensemble Based Box-Cox Transformation via Meta Analysis for Normality of a Variable

Description

boxcoxmeta performs ensemble based Box-Cox transformation via meta analysis for normality of a variable and provides graphical analysis.

Usage

```
boxcoxmeta(data, lambda = seq(-3,3,0.01), nboot = 100, lambda2 = NULL, plot = TRUE,
alpha = 0.05, verbose = TRUE)
```

Arguments

data	a numeric vector of data values.
lambda	a vector which includes the sequence of candidate lambda values. Default is set to (-3,3) with increment 0.01.
nboot	a number of Bootstrap samples to estimate standard errors of lambda estimates.
lambda2	a numeric for an additional shifting parameter. Default is set to lambda2 = 0.
plot	a logical to plot histogram with its density line and qqplot of raw and transformed data. Defaults plot = TRUE.
alpha	the level of significance to check the normality after transformation. Default is set to alpha = 0.05.
verbose	a logical for printing output to R console.

Details

Denote y the variable at the original scale and y' the transformed variable. The Box-Cox power transformation is defined by:

$$y' = \begin{cases} \frac{y^\lambda - 1}{\lambda}, & \text{if } \lambda \neq 0 \\ \log(y), & \text{if } \lambda = 0 \end{cases}$$

If the data include any nonpositive observations, a shifting parameter λ_2 can be included in the transformation given by:

$$y' = \begin{cases} \frac{(y + \lambda_2)^\lambda - 1}{\lambda}, & \text{if } \lambda \neq 0 \\ \log(y + \lambda_2), & \text{if } \lambda = 0 \end{cases}$$

Value

A list with class "boxcoxmeta" containing the following elements:

method	name of method
lambda.hat	estimate of Box-Cox Power transformation parameter
lambda2	additional shifting parameter
result	a data frame containing the result
alpha	the level of significance to assess normality.
tf.data	transformed data set
var.name	variable name

Author(s)

Muhammed Ali Yilmaz, Osman Dag

References

Yilmaz, M.A., Dag, O. (2022). Ensemble Based Box-Cox Transformation via Meta Analysis. *Journal of Advanced Research in Natural and Applied Sciences*, **8:3**, 463–471.

Examples

```
library(AID)
data(textile)

out <- boxcoxmeta(textile[,1])
out$lambda.hat # the estimate of Box-Cox parameter
out$tf.data # transformed data set
```

Description

boxcoxnc performs Box-Cox transformation for normality of a variable and provides graphical analysis.

Usage

```
boxcoxnc(data, method = "sw", lambda = seq(-3,3,0.01), lambda2 = NULL, plot = TRUE,
alpha = 0.05, verbose = TRUE)
```

Arguments

<code>data</code>	a numeric vector of data values.
<code>method</code>	a character string to select the desired method to be used to estimate Box-Cox transformation parameter. To use Shapiro-Wilk test method should be set to "sw". For method = "ad", boxcoxnc function uses Anderson-Darling test to estimate Box-Cox transformation parameter. Similarly, method should be set to "cvm", "pt", "sf", "lt", "jb", "ac", "mle" to use Cramer-von Mises, Pearson Chi-square, Shapiro-Francia, Lilliefors, Jarque-Bera tests, artificial covariate method and maximum likelihood estimation, respectively. Default is set to method = "sw".
<code>lambda</code>	a vector which includes the sequence of candidate lambda values. Default is set to (-3,3) with increment 0.01.
<code>lambda2</code>	a numeric for an additional shifting parameter. Default is set to lambda2 = 0.
<code>plot</code>	a logical to plot histogram with its density line and qqplot of raw and transformed data. Defaults plot = TRUE.
<code>alpha</code>	the level of significance to check the normality after transformation. Default is set to alpha = 0.05.
<code>verbose</code>	a logical for printing output to R console.

Details

Denote y the variable at the original scale and y' the transformed variable. The Box-Cox power transformation is defined by:

$$y' = \begin{cases} \frac{y^\lambda - 1}{\lambda}, & \text{if } \lambda \neq 0 \\ \log(y), & \text{if } \lambda = 0 \end{cases}$$

If the data include any nonpositive observations, a shifting parameter λ_2 can be included in the transformation given by:

$$y' = \begin{cases} \frac{(y + \lambda_2)^{\lambda} - 1}{\lambda}, & \text{if } \lambda \neq 0 \\ \log(y + \lambda_2), & \text{if } \lambda = 0 \end{cases}$$

Value

A list with class "boxcoxnc" containing the following elements:

<code>method</code>	method preferred to estimate Box-Cox transformation parameter
<code>lambda.hat</code>	estimate of Box-Cox Power transformation parameter based on corresponding method
<code>lambda2</code>	additional shifting parameter
<code>statistic</code>	statistic of normality test for transformed data based on specified normality test in method. For artificial covariate method, statistic is obtained by Shapiro-Wilk test for transformed data

p.value	p.value of normality test for transformed data based on specified normality test in method. For artificial covariate method, p.value is obtained by Shapiro-Wilk test for transformed data
alpha	the level of significance to assess normality.
tf.data	transformed data set
var.name	variable name

Author(s)

Osman Dag, Ozgur Asar, Ozlem Ilk

References

- Asar, O., Ilk, O., Dag, O. (2017). Estimating Box-Cox Power Transformation Parameter via Goodness of Fit Tests. *Communications in Statistics - Simulation and Computation*, **46:1**, 91–105.
- Dag, O., Asar, O., Ilk, O. (2014). A Methodology to Implement Box-Cox Transformation When No Covariate is Available. *Communications in Statistics - Simulation and Computation*, **43:7**, 1740–1759.

Examples

```
library(AID)

data(textile)

out <- boxcoxnc(textile[,1], method = "sw")
out$lambda.hat # the estimate of Box-Cox parameter based on Shapiro-Wilk test statistic
out$p.value # p.value of Shapiro-Wilk test for transformed data
out$tf.data # transformed data set
confInt(out) # mean and confidence interval for back transformed data

out2 <- boxcoxnc(textile[,1], method = "sf")
out2$lambda.hat # the estimate of Box-Cox parameter based on Shapiro-Francia test statistic
out2$p.value # p.value of Shapiro-Francia test for transformed data
out2$tf.data
confInt(out2)
```

Description

confInt.boxcoxfr calculates mean and asymmetric confidence interval for back transformed data in each group and plots their error bars with confidence intervals.

Usage

```
## S3 method for class 'boxcoxfr'
confInt(x, level = 0.95, plot = TRUE, xlab = NULL, ylab = NULL, title = NULL,
        width = NULL, verbose = TRUE, ...)
```

Arguments

<code>x</code>	a <code>boxcoxfr</code> object.
<code>level</code>	the confidence level.
<code>plot</code>	a logical to plot error bars with confidence intervals.
<code>xlab</code>	a label for the x axis, defaults to a description of <code>x</code> .
<code>ylab</code>	a label for the y axis, defaults to a description of <code>y</code> .
<code>title</code>	a main title for the plot.
<code>width</code>	a numeric giving the width of the little lines at the tops and bottoms of the error bars (defaults to 0.15).
<code>verbose</code>	a logical for printing output to R console.
<code>...</code>	additional argument(s) for methods.

Details

Confidence interval in each group is constructed separately.

Value

A matrix with columns giving mean, lower and upper confidence limits for back transformed data. These will be labelled as $(1 - \text{level})/2$ and $1 - (1 - \text{level})/2$ in % (by default 2.5% and 97.5%).

Author(s)

Osman Dag

Examples

```
library(AID)

data(AADT)
attach(AADT)
out <- boxcoxfr(aadt, class)
confInt(out, level = 0.95)
```

confInt.boxcoxmeta *Mean and Asymmetric Confidence Interval for Back Transformed Data*

Description

confInt.boxcoxmeta calculates mean and asymmetric confidence interval for back transformed data.

Usage

```
## S3 method for class 'boxcoxmeta'  
confInt(x, level = 0.95, verbose = TRUE, ...)
```

Arguments

x	a boxcoxmeta object.
level	the confidence level.
verbose	a logical for printing output to R console.
...	additional argument(s) for methods.

Value

A matrix with columns giving mean, lower and upper confidence limits for back transformed data. These will be labelled as $(1 - \text{level})/2$ and $1 - (1 - \text{level})/2$ in % (by default 2.5% and 97.5%).

Author(s)

Osman Dag, Muhammed Ali Yilmaz

Examples

```
library(AID)  
data(textile)  
  
out <- boxcoxmeta(textile[,1])  
confInt(out) # mean and confidence interval for back transformed data
```

confInt.boxcoxnc*Mean and Asymmetric Confidence Interval for Back Transformed Data***Description**

`confInt` is a generic function to calculate mean and asymmetric confidence interval for back transformed data.

Usage

```
## S3 method for class 'boxcoxnc'
confInt(x, level = 0.95, verbose = TRUE, ...)
```

Arguments

- `x` a `boxcoxnc` object.
- `level` the confidence level.
- `verbose` a logical for printing output to R console.
- `...` additional argument(s) for methods.

Value

A matrix with columns giving mean, lower and upper confidence limits for back transformed data. These will be labelled as $(1 - \text{level})/2$ and $1 - (1 - \text{level})/2$ in % (by default 2.5% and 97.5%).

Author(s)

Osman Dag

Examples

```
library(AID)

data(textile)
out <- boxcoxnc(textile[,1])
confInt(out) # mean and confidence interval for back transformed data
```

grades

Student Grades Data

Description

Overall student grades for a class taught by Dr. Ozlem Ilk

Usage

```
data(grades)
```

Format

A data frame with 42 observations on the following variable.

grades a numeric vector for the student grades

Examples

```
library(AID)

data(grades)
hist(grades[,1])
out <- boxcoxnc(grades[,1])
confInt(out, level = 0.95)
```

textile

Textile Data

Description

Number of Cycles to Failure of Worsted Yarn

Usage

```
data(textile)
```

Format

A data frame with 27 observations on the following variable.

textile a numeric vector for the number of cycles

References

Box, G. E. P., Cox, D. R. (1964). An Analysis of Transformations (with discussion). *Journal of the Royal Statistical Society, Series B (Methodological)*, **26**, 211–252.

Examples

```
library(AID)

data(textile)
hist(textile[,1])
out <- boxcoxnc(textile[,1])
confInt(out)
```

Index

* datasets

AADT, [2](#)
grades, [15](#)
textile, [15](#)

* functions

boxcoxfr, [3](#)
boxcoxlm, [6](#)
boxcoxmeta, [8](#)
boxcoxnc, [9](#)
confInt.boxcoxfr, [11](#)
confInt.boxcoxmeta, [13](#)
confInt.boxcoxnc, [14](#)

AADT, [2](#)

AID-package, [2](#)

boxcoxfr, [3](#)
boxcoxlm, [6](#)
boxcoxmeta, [8](#)
boxcoxnc, [9](#)

confInt (confInt.boxcoxnc), [14](#)

confInt.boxcoxfr, [11](#)

confInt.boxcoxmeta, [13](#)

confInt.boxcoxnc, [14](#)

grades, [15](#)

textile, [15](#)